
Registering Ignition Voice Alarm Module to CUCM

Zone Vang Principal Network and Collaboration Engineer 5-24-2018


NOTE: To register Ignition please register by creating a Third-Party SIP Device (Do not register Ignition via SIP TRUNK!). Also note if you do have a SIP trunk created already to your Ignition server you will have a conflict with your Third-Party SIP Device not registering to Ignition.

Step 1: User Management → End User → Select "Add New"




Step 2: Create user with digest credentials


NOTE: Use the extension as the username. Ignition will not register to Third Party SIP if you are using regular characters



Step 3: Device → Phone → Select "Add New"



Step 4: Select Third-party SIP Device (Basic) as your phone type



Step 5: For phone configuration, configure everything as usual. For digest user, use the end user you created at the start.

NOTE: You do not need an actually mac address (You can use 0000000000). Also you do not need an owner user ID. You would only need a digest user to register Ignition to CUCM

vetem - Call Positing - Media De	sources ▼ Advanced Features ▼ Devic	e - Application -	. Usar Management	t - Bulk Administration -
ystem ▼ Call Routing ▼ Intenta Re	Sources Advanced Features Devic	e Application	Oser Management	Duik Administration V
hone Configuration				
Save				
⊏Remote Number				1
Calling Party Transformation CSS	/ None >	*		
■ Use Device Pool Calling Party	Transformation CSS (Device Mobility Re	lated Information)		
Protocol Specific Information –				<u></u>
Protocol Specific Information -				
	FIRST CONTRACTOR VINES AND	2001		
BLF Presence Group*	Standard Presence group	•		
BLF Presence Group* MTP Preferred Originating Codec*	711ulaw	*		
BLF Presence Group*				
BLF Presence Group* MTP Preferred Originating Codec*	711ulaw	•		
BLF Presence Group* MTP Preferred Originating Codec* Device Security Profile*	711ulaw Not Selected < None >	v •		
BLF Presence Group* MTP Preferred Originating Codec* Device Security Profile* Rerouting Calling Search Space	711ulaw Not Selected < None >	* * * * * * * * * * * * * * * * * * *	iew Details	
BLF Presence Group* MTP Preferred Originating Codec* Device Security Profile* Rerouting Calling Search Space SUBSCRIBE Calling Search Space	711ulaw Not Selected < None > < None >	v v v	iew Details Find	
BLF Presence Group* MTP Preferred Originating Codec* Device Security Profile* Rerouting Calling Search Space SUBSCRIBE Calling Search Space SIP Profile* Digest User	711ulaw Not Selected < None > < None > < None > < None >	v v v		
BLF Presence Group* MTP Preferred Originating Codec* Device Security Profile* Rerouting Calling Search Space SUBSCRIBE Calling Search Space SIP Profile*	711ulaw Not Selected < None > < None > < None > < None >	v v v		

Step 6: For line configuration, configure how you would usually configure a line

NOTE: You do not need a user associated to the line